


Small Project Quilted Pouch with Pockets

Made using the Small Project 14" Skinny Robin or Fat Robin Compass Sunflower block.

Extra yardage needed in addition to Compass Sunflower found on Page 3 of this pattern.


Construction

- 1 Make the Skinny Robin OR Fat Robin 16-point 14" Compass Sunflower Block following the instructions starting on Page 2 in the **Companion Compass**(2nd) chapter of my Skinny Robin or Fat Robin 16-Point Book. **Note: Strips are cut for a 14" OctaCompass Sunflower from Page 4 of the OctaCompass (4th) chapter of your Skinny Robin or Fat Robin Book for an OctaCompass Sunflower. Center finished using the reverse appliqué technique.**




14" 16-Point Skinny Robin Compass Sunflower Block

OR




14" 16-Point Fat Robin Compass Sunflower Block


- 2 Use OctaCompass instructions found on Pages 2 and 3 of the OctaCompass (4th) chapter of either your Skinny Robin or Fat Robin Book. You will need two 5½" squares cut on the diagonal to finish the corners of your block. Examples below show if you use the same or contrasting fabric for the corners.



- 3 Cut two strips 1¼"x 14½" and sew them to the sides of your Skinny Robin or Fat Robin block. Cut one rectangle 5"x16" and add it to the bottom of your block. Press the seams toward the added strips to complete your Compass Unit.




- 4 Cut the two Pocket fabrics that will show inside your pouch. Cut the shorter Pocket 8"x16" and the taller Pocket 10"x16".



- 5 Cut the lining pieces and batting. I like to cut these a bit larger for quilting. Cut the lining and batting for the Compass Sunflower unit 18"x21", the shorter Pocket lining 10"x18", and the taller Pocket lining 12"x18". Sandwich the appropriate pieces together with batting and quilt by hand, on your domestic machine, or on your longarm. **Trim lining and batting flush with fronts when done quilting.** Note: If quilting on your longarm, use a yard of fabric for the lining and then place the Compass Sunflower unit and two pockets on top with batting to quilt.




- 6 Cut three full width strips that are 2½" wide for binding. Prepare one strip separately into binding for the Pockets by folding in half lengthwise with wrong sides together and pressing. Sew the other two strips together into a longer strip and prepare in the same manner.




- 7 Bind the top of the two quilted pockets. Cut the single binding strip in half and add on the top side of the shorter and taller pockets. Fold binding over to the lining side and stitch by hand or machine.




- 8 Layer the taller and shorter pocket on the lining side of the Compass Sunflower block unit and flush with the bottom. Pin in place. Add the pieced piece binding to the perimeter of your unit. Sew the binding on the outside of the unit and fold over to the lining side. Stitch by hand or machine.



- 9 Fold Compass Sunflower over at the middle point of the block. Add a closure (velcro, snap, or magnetic closure) at the x.



Yardage needed for Quilted Pouch in addition to Compass Sunflower Block



Batting needed for Quilted Pouch

If quilting on your longarm, I recommend using 1 yard.

